
DoSA Use Manual

Solenoid Example

2017-11-18

http://OpenActuator.org (zgitae@gmail.com)

Program Composition



Program Toolbar


1. Operations

✓ New : Create a new design

✓ Open : Open previous design

✓ Save : Save the design

✓ SaveAs : Save in different name



2. Design

✓ Coil : Add a coil and specification design

✓ Magnet : Add a magnet and determine specifications

✓ Steel : Add a steel and determine specifications



3. Experiment

✓ Force : Magnetic force estimation for driving part


✓ Stroke : Magnetic force estimation for each stroke

✓ Current : Magnetic force estimation for each current



Analysis Model Explanation

1. Model Shape



2. Product Specifications

가. Coil Turns

• Coil Turns: 1040 turns

• Coil Resistance: 15.2 Ohm

나. Power

• Voltage : 14.5V

(Work Example File : DoSA Install Directory > Samples > Solenoid)

Design Creation


1. Toolbar > Click New Button



2. Design Name: "Solenoid"

3. Click OK







Coil Creation


1. Toolbar > Click Coil button



- 2. Coil Name: "coil"
- 3. Coil Shape Input
 - ✓ Coil Location: Base_X 4.8, Base_Y -2
 - ✓ Left-Down Point : X 0, Y 0 (Relative Coordinates)
 - (Relative Coordinates
 - ✓ Right-Upper Point : X 6, Y 16 (Relative Coordinates)
- 4. Screen Adjustment : Use Fit All Button
- 5. Click OK Button
- 6. Check Shape (FEMM Window))







Coil Design

- 1. Input Coil specifications
 - ✓ Part Material : Copper Selection
 - ✓ Current Direction : IN Selection (Inner Direction)
 - ✓ Moving Parts: FIXED Selection (Fixed Parts)
 - ✓ Coil Wire Grade : Enameled_IEC_Grade_2 Selection
 - ✓ Copper Diameter : Enter 0.27 mm
 - ✓ Horizontal Coefficient : Base Value
 - ✓ Vertical Coefficient : Base Value
 - ✓ Resistance Coefficient : Base Value
- 2. Coil Specification calculation
 - ✓ Click Coil Design Button



1		
Δ	■ Common Fields	
	Node Name	coil
Δ	Specification Fields	
	Part Material	Copper
	Curent Direction	IN
	Moving Parts	FIXED
4	Calculated Fields	
	Coil Turns	1040
	Coil Resistance [Ω]	15, 20945
	Coil Layers	20
	Turns of One Layer	52
4	Design Fields (optional)	
	Coil Wire Grade	Enameled_IEC_Grade_2
	Inner Diameter [mm]	9,6
	Outer Diameter [mm]	21,6
	Coil Height [mm]	16
	Copper Diameter [mm]	
	Wire Diameter [mm]	0,31072
	Coil Temperature [°C]	
	Horizontal Coefficient	0.9
	Vertical Coefficient	0,98
	Resistance Coefficient	1

Plunger Creation

1. Toolbar > Click Steel Button




- 2. Steel Name: "plunger"
- 3. Face Type: RECTANGLE
- 4. Plunger Shape Input
 - ✓ Plunger Location : Base_X 0, Base_Y -12
 - ✓ Left-Down Point : X 0, Y 0


(Relative Coordinates)


✓ Right-Upper Point: X 4, Y 12

(Relative Coordinates)

- 5. Screen Adjustment : Use Fit All Button
- 6. Click OK Button
- 7. Check Shape (FEMM Window))








Plunger Settings

1. Plunger Specification setting

✓ Part Material: 430 Stainless Steel Selection

✓ Moving Parts : Moving Selection (Moving Parts)

[BH Curve]




■ Common Fields Node Name plunger Specification Fields 430 Stainless Steel Part Material Moving Parts MOVING


Core Creation

1. Toolbar > Click Steel Button



- 2. Steel Name: "core"
- 3. Add Coordinate (Total 6): Click 'A' Button
- 4. Input Core Shape
 - ✓ Core Location : Base_X 0, Base_Y 1.2
 - ✓ 1 점: X 0, Y 0
 - ✓ 2 점: X 4, Y 0
 - ✓ 3 점: X 4, Y 13.6
 - ✓ 4 점: X 15.6, Y 13.6
 - ✓ 5 점: X 15.6, Y 18
 - ✓ 6 점: X 0, Y 18
- 5. Screen Adjustment : Use Fit All Button
- 6. Click OK Button






Core Settings


7. Check Shape (FEMM Window)

8. Core Specification setting

✓ Part Material : 430 Stainless Steel

✓ Moving Parts : FIXED









Case Creation

1. Toolbar > Click Steel Button



- 2. Steel Name: "case"
- 3. Add Coordinate (Total 6): Click 'A' Button
- 4. Input Case Shape
 - ✓ Case Location: Base_X 4.4, Base_Y -10.4
 - ✓ 1 점: X 0, Y 0
 - ✓ 2 점: X 11.2, Y 0
 - ✓ 3 점: X 11.2, Y 25.2
 - ✓ 4 점: X 7.4, Y 25.2
 - ✓ 5 점: X 7.4, Y 7.6
 - ✓ 6 점: X 0, Y 7.6
- 5. Screen Adjustment : Use Fit All Button
- 6. Click OK Button






Case Setting


7. Check Shape (FEMM Window)


8. Case Specification setting

✓ Part Material: 1010 Steel

✓ Moving Parts : FIXED









Magnetic Force Experiment

1. Toolbar > Click Force Button



- 2. Force Experiment Name: "force"
- 3. Click OK Button
- 4. Magnetic Force Experiment Settings
 - ✓ Voltage: 14.5 V
- 5. Run Magnetic Force Experiment








Magnetic Force Experiment Results

1. Force: 12.57 N



Displacement-Magnetic Force Experiment

1. Toolbar > Click Stroke Button



2. Stroke Experiment Name: "stroke"

3. Click OK Button

4. Magnetic Force-Current Experiment Settings


✓ Voltage: 14.5 V

✓ Initial Stroke: 0.0 mm

✓ Final Stroke: 1.0 mm


✓ Step Count: 5





Displacement-Magnetic Force Experiment Results

1. Information View / Click Stroke Test Button



Current-Magnetic Force Experiment

1. Toolbar > Click Current Button



2. Current Experiment Name: "current"


3. Click OK Button


4. Magnetic Force-Current Experiment Settings

✓ Initial Current: 0.0 A

✓ Final Current: 1.5 A


✓ Step Count: 5





Current-Magnetic Force Experiment Results

1. Information View / Click Current Test Button



- Thank You -