


DoSA Use Manual

Linear Vibrator (VCM function) example

2017-11-18

<http://OpenActuator.org> (zgita@gmail.com)


Program Composition



Program Toolbar

1. Operations

- ✓ New : Create a new design
- ✓ Open : Open previous design
- ✓ Save : Save the design
- ✓ SaveAs : Save in different name




2. Design

- ✓ Coil : Add a coil and specification design
- ✓ Magnet : Add a magnet and determine specifications
- ✓ Steel : Add a steel and determine specifications




3. Experiment

- ✓ Force : Magnetic force estimation for driving part
- ✓ Stroke : Magnetic force estimation for each stroke
- ✓ Current : Magnetic force estimation for each current



Analysis Model Explanation

1. Shape Model



2. Product Specifications

가. Coil

- Coil Turns : 126 turns
- Coil Resistance : 15.75 Ohm

나. Magnet

- Material : NdFeB 52
- Magnetization Direction : 90 (UP)

다. Power

- Voltage : 2.5V


(Example File: DoSA Install directory > Samples > LV)

Design Creation


1. Toolbar > Click New button
2. Design Name : "LV"
3. Click OK



2



3



Create new design

Coil Creation

1. Toolbar > Click Coil button



2. Coil Name : "coil"


3. Input the coil shape Input

- ✓ Coil Location : Base_X 1.5, Base_Y -0.67
- ✓ Left-down point : X 0, Y 0
(Relative coordinates)
- ✓ Right-Up Point : X 0.365, Y 1.18
(Relative coordinates)


4. Screen Adjustment : Use Fit All button

5. Click OK button


6. Check shape (FEMM Window)



2~4



5



Coil Design

1. Input the coil instrumental specifications
 - ✓ Part Material : Select Copper
 - ✓ Current Direction : Select IN (Inner direction)
 - ✓ Moving Parts : Select FIXED (Fixed Components)
 - ✓ Coil Wire Grade : Bonded_IEC_Grade_1B Selection
 - ✓ Copper Diameter : 0.045 mm selection
 - ✓ Horizontal Coefficient : 0.95 Selection
 - ✓ Vertical Coefficient : 1.13 Selection
 - ✓ Resistance Coefficient : 1.1 Selection
2. Coil specification calculation
 - ✓ Click Design Coil Button


2


Coil Design

1


Common Fields	
Node Name	coil
Specification Fields	
Part Material	Copper
Current Direction	IN
Moving Parts	FIXED
Calculated Fields	
Coil Turns	126
Coil Resistance [Ω]	15,74769
Coil Layers	6
Turns of One Layer	21
Design Fields (optional)	
Coil Wire Grade	Bonded_IEC_Grade_1B
Inner Diameter [mm]	3
Outer Diameter [mm]	3,73
Coil Height [mm]	1,18
Copper Diameter [mm]	0,045
Wire Diameter [mm]	0,04953
Coil Temperature [$^{\circ}\text{C}$]	20
Horizontal Coefficient	0,95
Vertical Coefficient	1,13
Resistance Coefficient	1,1

Magnet Creation


1. Toolbar > Click Magnet button 
2. Magnet Name : "magnet"
3. Magnet Shape Selection
 - ✓ Magnet location : Base_X 0, Base_Y 0.4
 - ✓ Left-down Point : X 0, Y 0
(Relative Coordinates)
 - ✓ Right-Up point : X 1.35, Y 1
(Relative Coordinates)
4. Screen Adjustment : Use Fit All button
5. Click OK button
6. Confirm Shape (FEMM window)



2~4




5



Magnet Settings

1. Magnet Settings

- ✓ Part Material : NdFeB 52 MGOe Selection
- ✓ Direction : UP
- ✓ Moving Parts : Moving Selection (Moving parts)



1

Common Fields

Node Name magnet

Specification Fields

Part Material NdFeB 52 MGOe

Direction UP

Moving Parts MOVING

Plate Creation

1. Toolbar > Click Steel Button



2. Steel Name : "plate"

3. Face Type : RECTANGLE Selection

4. Plate Shape Selection

✓ 자석 위치 : Base_X 0, Base_Y 0.2


✓ Left-down point : X 0, Y 0
(Relative Coordinates)

✓ Right-Up point : X 1.35, Y 0.2
(Relative Coordinates)


5. Screen Adjustment : Use Fit All button

6. Click OK button


7. Shape confirm (FEMM window)



2~5



6



Yoke Creation

1. Toolbar > Click Steel Button



2. Steel Name : "yoke"

3. Coordinate addition (total 8) :Click 'A'


4. Yoke Shape Selection

- ✓ Yoke location : Base_X 0, Base_Y 0.2
- ✓ 1 Point : X 0, Y 1.4
- ✓ 2 Point : X 0, Y 1.2
- ✓ 3 Point : X 1.9, Y 1.2 (Arc, Dir check)
- ✓ 4 Point : X 2.05, Y 1.05
- ✓ 5 Point : X 2.05, Y 0
- ✓ 6 Point : X 2.25, Y 0
- ✓ 7 Point : X 2.25, Y 1.05 (Arc check)
- ✓ 8 Point : X 1.9, Y 1.4

5. Screen Adjustment : Use Fit All button


6. Click OK button

2~3

The "Add Steel" dialog box is shown. It has fields for "Steel Name" (yoke) and "Face Type" (POLYGON). Below these are "Base_X" (0.0) and "Base_Y" (0.0). A table with 8 rows and 7 columns (No., X, Y, Arc, Dir, Del, Add) is present. The "Add" column has a button labeled 'A' next to the last row. At the bottom are buttons for "Redraw", "Fit All", "Reserved", "OK", and "Cancel".

No.	X	Y	Arc	Dir	Del	Add
1			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
2			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
3			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
4			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
5			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
6			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
7			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
8			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/> <input type="button" value="A"/>



4~5

The "Add Steel" dialog box is shown. It has fields for "Steel Name" (yoke) and "Face Type" (POLYGON). Below these are "Base_X" (0.0) and "Base_Y" (0.2). A table with 8 rows and 7 columns (No., X, Y, Arc, Dir, Del, Add) is present. The "Add" column has a button labeled 'A' next to the last row. At the bottom are buttons for "Redraw", "Fit All", "Reserved", "OK", and "Cancel".

No.	X	Y	Arc	Dir	Del	Add
1	0	1.4	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
2	0	1.2	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
3	1.9	1.2	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
4	2.05	1.05	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
5	2.05	0	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
6	2.25	0	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
7	2.25	1.05	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/>
8	1.9	1.4	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="button" value="D"/> <input type="button" value="A"/>

Creating Yoke

7. Shape confirmation (FEMM window)




Plate, Yoke settings

1. Plate, Yoke settings

- ✓ Part Material : 430 Stainless Steel Selection
- ✓ Moving Parts : Moving Selection (Moving Parts)

[BH curve]



1

Common Fields

Node Name plate

Specification Fields

Part Material 430 Stainless Steel

Moving Parts MOVING

Magnetic force Experiment

1. Toolbar > Click Force Button



2. Force Experiment Name : "force"


3. Click OK button

4. Magnetic force experiment settings

✓ Voltage : 2.5 V

5. Run Magnetic force experiment

2~3



4


Common Fields	
Node Name	force
Input Fields	
Voltage [V]	2,5
Max. Current [A]	0,15875
Stroke Fields	
Moving Stroke [mm]	0

5



Magnetic Force Experiment Results

1. Force : -0.05428 N



Displacement-Magnetic Force Experiment

1. Toolbar > Click Stroke button




2. Stroke Experiment Name : "stroke"

3. Click OK button

4. Magnetic force-Current experiment settings

- ✓ Voltage : 2.5 V
- ✓ Initial Stroke : -0.5 mm
- ✓ Final Stroke : 0.5 mm
- ✓ Step Count : 5

2~3




4

Common Fields	
Node Name	stroke
Input Fields	
Voltage [V]	2.5
Max. Current [A]	0.15875
Stroke Fields	
Initial Stroke [mm]	-0.5
Final Stroke [mm]	0.5
Step Count	5

Displacement-Magnetic Force Experiment Results

1. Information View / Click Stroke Test button



Current-Magnetic force experiment

1. Toolbar > Click Current button




2. Current Experiment Name : "current"

3. Click OK button

4. Magnetic force-Current experiment settings

- ✓ Initial Current : 0.0 A
- ✓ Final Current : 0.1 A
- ✓ Step Count : 5

2~3



4

Common Fields	
Node Name	current
Current Fields	
Initial Current [A]	0
Final Current [A]	0.1
Step Count	5
Stroke Fields	
Moving Stroke [mm]	0


Current-Magnetic Force experiment results

1. Information View / Click Current Test button

1

Current Test

Result





– Thank You –
