


DoSA User Manual

Example of Linear Vibrator




2018-04-21

GiTae Kweon (zgitae@gmail.com)

DoSA Structure

Program Structure



Toolbar

1. Operations

- ✓ New : Create a new design
- ✓ Open : Open previous design
- ✓ Save : Save the design
- ✓ SaveAs : Save in different name




2. Design

- ✓ Coil : Add a coil and specification design
- ✓ Magnet : Add a magnet and determine specifications
- ✓ Steel : Add a steel and determine specifications



3. Experiment


- ✓ Force : Magnetic force estimation for driving part
- ✓ Stroke : Magnetic force estimation for each stroke
- ✓ Current : Magnetic force estimation for each current



Analysis Model

Analysis Model

1. Shape Model



2. Product Specifications

가. Coil

- Coil Turns : 126 turns
- Coil Resistance : 15.75 Ohm

나. Magnet

- Material : NdFeB 52
- Magnetization Direction : 90 (UP)

다. Power

- Voltage : 2.5V


(Example Files : DoSA Install directory > Samples > LV)

New design


1. Toolbar > Click New button
2. Design Name : "LV"
3. Click OK



2



3




Create new design


Parts Design

Add coil


1. Toolbar > Click Coil button
2. Coil Name : "coil"
3. Input the coil shape
 - ✓ Coil Location : Base_X 1.5, Base_Y -0.67
 - ✓ Left-down point : X 0, Y 0
(Relative coordinates)
 - ✓ Right-Up Point : X 0.365, Y 1.18
(Relative coordinates)
4. Screen Adjustment : Use Fit All button
5. Click OK button
6. Check shape (FEMM Window)



2~4



5



Coil Design

1. Input the coil instrumental specifications
 - ✓ Part Material : Select Copper
 - ✓ Current Direction : Select IN (Inner direction)
 - ✓ Moving Parts : Select FIXED (Fixed Components)
 - ✓ Coil Wire Grade : Bonded_IEC_Grade_1B
 - ✓ Copper Diameter : 0.045 mm
 - ✓ Horizontal Coefficient : 0.95 (Bonded Type)
 - ✓ Vertical Coefficient : 1.13 (Bonded Type)
 - ✓ Resistance Coefficient : 1.1 (Bonded Type)
2. Calculate the coil specification
 - ✓ Click the "Coil Design" button

2

Coil Design


1

Common Fields	
Node Name	coil
Specification Fields	
Part Material	Copper
Current Direction	IN
Moving Parts	FIXED
Calculated Fields	
Coil Turns	126
Coil Resistance [Ω]	15,74769
Coil Layers	6
Turns of One Layer	21
Design Fields (optional)	
Coil Wire Grade	Bonded_IEC_Grade_1B
Inner Diameter [mm]	3
Outer Diameter [mm]	3,73
Coil Height [mm]	1,18
Copper Diameter [mm]	0,045
Wire Diameter [mm]	0,04953
Coil Temperature [$^{\circ}\text{C}$]	20
Horizontal Coefficient	0,95
Vertical Coefficient	1,13
Resistance Coefficient	1,1


Add magnet




1. Toolbar > Click Magnet button
2. Magnet Name : "magnet"
3. Magnet Shape
 - ✓ Magnet location : Base_X 0, Base_Y 0.4
 - ✓ Left-down Point : X 0, Y 0
(Relative Coordinates)
 - ✓ Right-Up point : X 1.35, Y 1
(Relative Coordinates)
4. Screen Adjustment : Use Fit All button
5. Click OK button
6. Confirm Shape (FEMM window)



2~4




5



Magnet Settings

1. Magnet Settings

- ✓ Part Material : NdFeB 52 MGOe
- ✓ Direction : UP
- ✓ Moving Parts : MOVING (Moving parts)



1

Common Fields

Node Name magnet

Specification Fields

Part Material NdFeB 52 MGOe

Direction UP

Moving Parts MOVING

Add plate

1. Toolbar > Click Steel Button



2. Steel Name : "plate"

3. Face Type : RECTANGLE

4. Plate Shape

✓ 자석 위치 : Base_X 0, Base_Y 0.2


✓ Left-down point : X 0, Y 0
(Relative Coordinates)

✓ Right-Up point : X 1.35, Y 0.2
(Relative Coordinates)


5. Screen Adjustment : Use Fit All button

6. Click OK button


7. Shape confirm (FEMM window)



2~5



6



Add yoke

1. Toolbar > Click Steel Button



2. Steel Name : "yoke"

3. Add input lines of point : Click 'A' button


4. Yoke Shape

- ✓ Yoke location : Base_X 0, Base_Y 0.2
- ✓ 1 Point : X 0, Y 1.4
- ✓ 2 Point : X 0, Y 1.2
- ✓ 3 Point : X 1.9, Y 1.2 (Arc, Dir check)
- ✓ 4 Point : X 2.05, Y 1.05
- ✓ 5 Point : X 2.05, Y 0
- ✓ 6 Point : X 2.25, Y 0
- ✓ 7 Point : X 2.25, Y 1.05 (Arc check)
- ✓ 8 Point : X 1.9, Y 1.4

5. Screen Adjustment : Use Fit All button


6. Click OK button

2~3

A screenshot of the "Add Steel" dialog box. The "Steel Name" field contains "yoke" and the "Face Type" dropdown is set to "POLYGON". The "Base_X" and "Base_Y" fields are both set to 0.0. Below these is a table with 8 rows for points. The "No." column contains numbers 1 through 8. The "X" and "Y" columns are empty. The "Arc" and "Dir" columns have checkboxes. The "Del" column has a button labeled "D". The "Add" column has a button labeled "A". At the bottom are buttons for "Redraw", "Fit All", "Reserved", "OK", and "Cancel".

No.	X	Y	Arc	Dir	Del	Add
1			<input type="checkbox"/>	<input type="checkbox"/>	D	
2			<input type="checkbox"/>	<input type="checkbox"/>	D	
3			<input type="checkbox"/>	<input type="checkbox"/>	D	
4			<input type="checkbox"/>	<input type="checkbox"/>	D	
5			<input type="checkbox"/>	<input type="checkbox"/>	D	
6			<input type="checkbox"/>	<input type="checkbox"/>	D	
7			<input type="checkbox"/>	<input type="checkbox"/>	D	
8			<input type="checkbox"/>	<input type="checkbox"/>	D	A



4~5

A screenshot of the "Add Steel" dialog box, showing the same fields as the previous one but with the "Fit All" button highlighted in blue. The "Steel Name" field contains "yoke" and the "Face Type" dropdown is set to "POLYGON". The "Base_X" and "Base_Y" fields are both set to 0.2. Below these is a table with 8 rows for points. The "No." column contains numbers 1 through 8. The "X" and "Y" columns contain values: 0, 1.4, 0, 1.2, 1.9, 1.2, 2.05, 1.05, 2.05, 0, 2.25, 0, 2.25, 1.05, 1.9, 1.4. The "Arc" and "Dir" columns have checkboxes. The "Del" column has a button labeled "D". The "Add" column has a button labeled "A". At the bottom are buttons for "Redraw", "Fit All", "Reserved", "OK", and "Cancel".

No.	X	Y	Arc	Dir	Del	Add
1	0	1.4	<input type="checkbox"/>	<input type="checkbox"/>	D	
2	0	1.2	<input type="checkbox"/>	<input type="checkbox"/>	D	
3	1.9	1.2	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	D	
4	2.05	1.05	<input type="checkbox"/>	<input type="checkbox"/>	D	
5	2.05	0	<input type="checkbox"/>	<input type="checkbox"/>	D	
6	2.25	0	<input type="checkbox"/>	<input type="checkbox"/>	D	
7	2.25	1.05	<input checked="" type="checkbox"/>	<input type="checkbox"/>	D	
8	1.9	1.4	<input type="checkbox"/>	<input type="checkbox"/>	D	A

Add yoke

7. Shape confirmation (FEMM window)




Plate, Yoke settings

1. Plate, Yoke settings

- ✓ Part Material : 430 Stainless Steel
- ✓ Moving Parts : MOVING (Moving Parts)

[BH curve]



1

Common Fields	
Node Name	plate
Specification Fields	
Part Material	430 Stainless Steel
Moving Parts	MOVING

Virtual Experiments

Experiment of magnetic force

1. Toolbar > Click Force Button



2. Force Experiment Name : "force"


3. Click OK button

4. Settings of magnetic force experiment

✓ Voltage : 2.5 V

5. Click "Force Test" Button

2~3



4


Common Fields	
Node Name	force
Input Fields	
Voltage [V]	2,5
Max. Current [A]	0,15875
Stroke Fields	
Moving Stroke [mm]	0

5



Results of magnetic force


1. Force : -0.05428 N



Experiment of displacement–magnetic force



1. Toolbar > Click Stroke button
2. Stroke Experiment Name : "stroke"
3. Click OK button
4. Settings of the experiment
 - ✓ Voltage : 2.5 V
 - ✓ Initial Stroke : -0.5 mm
 - ✓ Final Stroke : 0.5 mm
 - ✓ Step Count : 5




4

Common Fields	
Node Name	stroke
Input Fields	
Voltage [V]	2.5
Max. Current [A]	0.15875
Stroke Fields	
Initial Stroke [mm]	-0.5
Final Stroke [mm]	0.5
Step Count	5

Results of displacement–magnetic force

5. Information View > Click “Stroke Test” button




Experiment of current-magnetic force

1. Toolbar > Click Current button
2. Experiment Name : "current"
3. Click OK button
4. Experiment settings
 - ✓ Initial Current : 0.0 A
 - ✓ Final Current : 0.1 A
 - ✓ Step Count : 5



2~3




4

Common Fields	
Node Name	current
Current Fields	
Initial Current [A]	0
Final Current [A]	0.1
Step Count	5
Stroke Fields	
Moving Stroke [mm]	0

Results of current-magnetic force

5. Information View > Click "Current Test" button



Thank You